**GRIDSTATS 2.0 USER'S MANUAL** 

# **GRIDSTATS 2.0 USER'S MANUAL**

### 1.0 INTRODUCTION

GridStats 2.0 was designed to share data directly with SiteStats 2.0. This allows SiteStats to use the full set of features available in the stand alone version of GridStats. Previous users will recall the limitations of the imbedded version of GridStats. Those hindrances have been removed.

# 2.0 GRIDSTATS EVALUATION SETUP

To sample a grid select New Grid Evaluation from the File menu as shown in Figure 1 below.




Figure 1. GridStats 2.0 Screen

Before sampling begins you are prompted to create a file in which all grid data will be stored. The file should be saved in Microsoft Excel format (.xls).

When prompted, enter the location and number of anomalies for the grid. (See Figure 2.) It is important that you do not leave any text field blank. If information is unknown then type "unknown" or "not available" into the text field. You must enter the number of anomalies. After you have entered the data press the OK button.




Figure 2. GridStats: General Inputs Screen

The grid dimensions and maximum clearance depth are required inputs. (See Figure 3.) Remember to enter the values in units of feet.




Figure 3. Dimensions Screen

Once the preliminary grid data has been entered, the software will select a grid sampling plan. The plan selection is displayed on the screen as shown in Figure 4. (Please refer to the SiteStats 1.0 User Manual for an explanation of sampling plans.)




Figure 4. Sampling Plan Selection Screen

# 3.0 GRIDSTATS SAMPLING

The GridStats sampling screen (Figure 5) provides the basic work area for recording data.




Figure 5. GridStats Sampling Screen

There are 4 types of anomalies to select from. Choose UXO, UXO Scrap/Shrapnel, Non-UXO False Positive or Surface UXO.

A text field exists for entering the depth of the anomaly. Enter the value in inches.

Click the Record This Sample command button to identify the anomaly.

Click the **Stop Sampling** command button to pause and return to the main screen.

Click the **No Anomalies - New Subgrid** command button when no anomalies are present in the current subgrid square.

Clicking the **Options** command button allows the user to specify the date and time or make a note for the current anomaly. (See Figure 6.)

Advanced Sample Options						
<u>D</u> ate:	01 Feb 96					
<u>T</u> ime:	11:31 AM					
<u>N</u> ote:	none					

Figure 6. Advanced Sample Options Screen

# 4.0 GRIDSTATS DATA QUERIES

Several ways of viewing grid data are available from the Data menu on the main screen. Each method of display is described below.




Figure 7. GridStats 2.0 Screen

View Map of UXO Locations: A map of the grid is displayed with locations of ordnance items marked in red. (Figure 8.)




Figure 8. Data Query: UXO Locations Screen

View Map of UXO Scrap Locations: A map of the grid is displayed with locations of scrap and shrapnel marked in black. (Figure 9.)




Figure 9. Data Query: Locations of UXO Scrap Screen

View Map of False Postive Locations: A map of the grid is displayed with locations of false positives marked in blue. (Figure 10.)




Figure 10. Data Query: Locations of False Positives Screen

View Map of Sampled Subgrids: A map of the grid is displayed with sample locations marked in green. (Figure 11.)




Figure 11. Data Query: Sample Locations Screen

**Search for Maximum Anomaly Depth:** The database is queried and the maximum anomaly depth is returned. (Figure 12.)




Figure 12. Data Query Result Screen

**Search for Maximum Ordnance Depth:** The database is queried and the maximum ordnance depth is returned. (Figure 13.)




Figure 13. Data Query Result Screen

Obtain Data on an Individual Sample: After entering the sample you wish to view, the data recorded for that sample is displayed. (Figure 15.)




Figure 14. Sample Selection Screen




Figure 15. Data Query Results Screen

**Obtain Data on an Individual Subgrid:** After entering the subgrid you wish to view, all data recorded in that subgrid is displayed. (Figure 17.)




Figure 16. Subgrid Selection Screen




Figure 17. Data Query Results Screen

Display Chart of Actual Sample Counts: A bar chart summarizes the actual sample data. (Figure 18.)




Figure 18. Summary: Actual Anomaly Data Screen

**Display Chart of Expected Sample Counts:** A bar chart summarizes the expected sample data for the grid. (Figure 19.)




Figure 19. Summary: Predicted Anomaly Data Screen

**Display Grid Sampling Summary:** A form appears with the summarized data for the grid. (Figure 20.)

# Bite Location: Camp Swampy Sector: Impact Range Grid: 1 Number of Samples: 10 Number of False Positives: 3 Number of UXO Scrap: 4 Number of UXO: 3 Expected Number of False Positives: 36 Expected Number of UXO Scrap: 48 Expected Number of UXO: 36 Number of Surface UXO: 0

Figure 20. Data Query Results Screen

**Display Grid Sampling Sequence:** A form appears with the complete data for each anomaly sampled within the grid. (Figure 21.)

Sampling Data Sequence									
Hide This Form									
	1	5	False Positive	12.00	2/1/96	11:31 AM			
	2	15	False Positive	16.00	2/1/96	11:32 AM			
	3	28	UXO	8.20	2/1/96	11:32 AM			
	4	27	UXO Scrap	22.00	2/1/96	11:32 AM			
	5	28	UXO	25.00	2/1/96	11:32 AM			
	6	3	UXO Scrap	18.00	2/1/96	11:32 AM			
	7	7	False Positive	32.0 <b>0</b>	2/1/96	11:32 AM			
	8	23	UXO Scran	13.00	2/1/96	11.32 AM			

Figure 21. Sampling Data Sequence Screen